Terminate the virtual machine named `mymachine` that you started at the beginning of this chapter by doing the following:

1. Go to EC2 in the AWS Management Console: https://console.aws.amazon.com/ec2/.
2. Open the list of all virtual machines and select Instances from the subnavigation options.
3. Select the running virtual machine by clicking the row in the table.
4. Click the Instance State button and select Terminate Instance.

3.4 Changing the size of a virtual machine

It is always possible to change the size of a virtual machine. This is one of the advantages of using the cloud, and it gives you the ability to scale vertically. If you need more computing power, increase the size of the EC2 instance, or vice versa.

In this section, you'll learn how to change the size of a running virtual machine. To begin, follow these steps to start a small virtual machine:

1. Go to EC2 in the AWS Management Console: https://console.aws.amazon.com/ec2/.
2. Click the Launch Instances button.
3. Enter growingup as the name of the virtual machine.
4. Choose the Amazon Linux 2 AMI.
5. Select instance type `t2.micro`.
6. Select the option Proceed without a Key Pair.
7. Keep the default for network and storage.
8. Select the IAM instance profile `ec2-ssm-core` under Advanced Details.