- Your web server needs to answer requests by using multiple TLS/SSL certificates, and you can’t use the Server Name Indication (SNI) extension due to legacy clients.
- You want to create a management network separated from the application network, and, therefore, your EC2 instance needs to be accessible from two networks. Figure 3.25 illustrates an example.
- Your application requires or recommends the use of multiple network interfaces (e.g., network and security appliances).




Figure 3.25 A virtual machine with two network interfaces in two different subnets

In the next procedure, you will use an additional network interface to connect a second public IP address to your EC2 instance. Follow these steps to create an additional networking interface for your virtual machine:

1. Open the Management Console, and go to the EC2 service.
2. Select Network Interfaces from the submenu. The default network interface of your virtual machine is shown in the list. Note the subnet ID of this network interface.
3. Click Create Network Interface.
4. Enter 2nd interface as the description, as shown in figure 3.26.
5. Choose the subnet you noted in step 3.
6. Select Auto-Assign Private IPv4 Address.