```
        if (err) {
          cb(err);
        } else {
          const subnetIds = data.Subnets.map(subnet => subnet.SubnetId);
          cb(null, subnetIds);
        }
      });
    }
  });
};
```

① API call to list VPCs

② The filter selects default VPCs only.

③ There can be only one default VPC.

④ API call to list subnets

⑤ The filter selects subnets from the default VPC only.

After you select the subnet, the virtual machine is created by lib/createVM.js, and you see a starting screen, as shown in the following listing.

Listing 4.5 Launching an EC2 instance: /lib/createVM.js

```
module.exports = (amiId, subnetId, cb) => {
  ec2.runInstances({                    ①
    IamInstanceProfile: {               ②
      Name: 'ec2-ssm-core'
    },
    ImageId: amiId,                     ③
    MinCount: 1,                        ④
    MaxCount: 1,                        ④
    InstanceType: 't2.micro',           ⑤
    SubnetId: subnetId                  ⑥
  }, cb);
};
```

① API call to launch an EC2 instance

② The IAM role and instance profile ec2-ssm-core was created in chapter 3.

③ Passes the selected AMI

④ Launches one instance...

⑤ ...of type t2.micro to stay in the Free Tier

⑥ Passes the selected subnet