- *Public subnets*—For all resources that need to be reachable from the internet, such as a load balancer of a internet-facing web application
- *Private subnets*—For all resources that should not be reachable from the internet, such as an application server or a database system

What's the difference between a public and private subnet? A public subnet has a route to the internet; a private subnet doesn't.

For the purpose of understanding how a VPC works, you'll create a VPC to replicate the example from the previous section. You'll implement the proxy concept from the previous section by creating a public subnet that contains only the proxy. You'll also create a private subnet for the backend servers. You will not be able to access a backend server directly from the internet because it will sit on a private subnet. The backend servers will be accessible only via the proxy server running in a public subnet.

The VPC uses the address space 10.0.0.0/16. To isolate different parts of the system, you'll add the next two public subnets and one private subnet to the VPC:

- *10.0.0.0/24*—Public subnet used later in this section to deploy a NAT gateway
- *10.0.1.0/24*—Public proxy subnet
- *10.0.2.0/24*—Private backend subnet

What does 10.0.0.0/16 mean?