```
    RuleAction: 'allow'
    Egress: 'true'
    CidrBlock: '0.0.0.0/0'
NetworkAclEntryOutPublicNATHTTPS:                    ⑤
  Type: 'AWS::EC2::NetworkAclEntry'
  Properties:
    NetworkAclId: !Ref NetworkAclPublicNAT
    RuleNumber: '110'
    Protocol: '6'
    PortRange:
      From: '443'
      To: '443'
    RuleAction: 'allow'
    Egress: 'true'
    CidrBlock: '0.0.0.0/0'
NetworkAclEntryOutPublicNATEphemeralPorts:           ⑥
  Type: 'AWS::EC2::NetworkAclEntry'
  Properties:
    NetworkAclId: !Ref NetworkAclPublicNAT
    RuleNumber: '200'
    Protocol: '6'
    PortRange:
      From: '1024'
      To: '65535'
    RuleAction: 'allow'
    Egress: 'true'
    CidrBlock: '10.0.0.0/16'
```

① Allows inbound HTTP from all VPC subnets

② Allows inbound HTTPS from all VPC subnets

③ Ephemeral ports

④ Allows outbound HTTP to everywhere

⑤ Allows outbound HTTPS to everywhere

⑥ Ephemeral ports

Finally, you can add the NAT gateway itself. The NAT gateway comes with a fixed public IP address (also called an Elastic IP address). All traffic that is routed through the NAT gateway will come from this IP address. We also add a route to the backend's route table to route traffic to 0.0.0.0/0 via the NAT gateway, as shown here:

```
EIPNatGateway:                                       ①
  Type: 'AWS::EC2::EIP'
```