You can now use the instance store by reading and writing to `/data` like this:

```
$ df -h
Filesystem      Size  Used Avail Use% Mounted on
[...]
/dev/nvme1n1    110G  145M  110G   1% /data      ①
```

① 110 GB are available.

Windows

For Windows instances, instance store volumes are NTFS formatted and mounted automatically.

8.2.2 Testing performance

Let’s take the same performance measurements we took in section 8.1.3 to see the difference between the instance store and EBS volumes, as shown next:

```
$ sudo dd if=/dev/zero of=/data/tempfile bs=1M count=1024 \
➥ conv=fdatasync,notrunc
1024+0 records in
1024+0 records out
1073741824 bytes (1.1 GB) copied, 13.3137 s, 80.6 MB/s     ①
$ echo 3 | sudo tee /proc/sys/vm/drop_caches
3

$ sudo dd if=/data/tempfile of=/dev/null bs=1M count=1024
1024+0 records in
1024+0 records out
1073741824 bytes (1.1 GB) copied, 5.83715 s, 184 MB/s      ②
sh-4.2$ echo 3 | sudo tee /proc/sys/vm/drop_caches
```

① 18% faster compared with EBS from section 8.1.3