- `sqs:DeleteMessage`, and `sqs:ReceiveMessage` to the SQS queue created in the template
- `s3:PutObject` to the S3 bucket created in the template to upload a file to S3 (You can further limit writes to the `processed/` key prefix.)
- `dynamodb:GetItem` and `dynamodb:UpdateItem` to the DynamoDB table created in the template

Both servers and workers need to grant access for the AWS Systems Manager to enable access via Session Manager as follows:

- `ssmmessages:*`
- `ssm:UpdateInstanceInformation`
- `ec2messages:*`

If you don't feel comfortable with IAM roles, take a look at the book's code repository on GitHub at https://github.com/AWSinAction/code3. The template with IAM roles can be found in /chapter16/template.yaml.

Now it's time to deploy the server.

Deploying the server with a load balancer and an Auto Scaling group

The Imagery server allows the user to upload images, monitor the processing, and show the results. An Application Load Balancer (ALB) acts as the entry point into the system. Behind the load balancer, a fleet of servers running on EC2 instances answers incoming HTTP requests. An Auto Scaling group ensures EC2