Sl. No.	Material required
6.	Soapy swab
7.	Wet and dry swab
8.	Pen and watch with second hand

Procedure:-

1. Bring the tray to the bedside and explain to the patient, who should be at rest, sitting or lying down
2. Make sure the patient has not just taken a bath or had a hot or cold drink within fifteen minutes
3. Take a thermometer from the lotion dip in clean water and wipe with cotton, using a circular movement from the bulb towards the hand. Avoid touching the part that goes into the mouth
4. Read the thermometer and be sure it is shakedown at 35°C (95°F) or below
5. Place the thermometer under the patient's tongue and instruct him not to bite it but to close his lips gently. He should not talk not cough
6. Keep the thermometer in the mouth for 1 to3 minutes (the time required may be written on the thermometer)
7. Place the tip of three fingers (never the thumb) gently cover the radial artery at the wrist
8. Feel the pulsation carefully before starting to count. Note the strength and regularity of the beats.
9. Using a watch with seconds hand or a pulseoxymeter, count the number of beats for one minute. It necessary, count longer to be sure and accurate
10. Feel or watch the rise and fall of the patient's chest
11. Count each rise and fall as one respiration. Count for a full minute.
12. While counting the rate, note also
    - (i) Rhythm - regular or irregular
    - (ii) Depth - Shallow, normal or deep
    - (iii) Sound - quiet or noisy
    - (iv) Any discomfort or difficulty in breathing
13. Record the temperature pulse and Respiration on the chart or in the TPR chart.
14. Taking and replacing thermometers should be in rotation making sure they remain in disinfectant for at least 3 minutes before being used for another patient.
15. After the procedure, clean and reset the tray for next use.

Blood Pressure:

Method of taking the Blood pressure

1. Explain the procedure to the patients and have him seated by a table or lying with the arm supported and relaxed.
2. Place the centre of the cuff of the BP apparatus over the brachial artery and wrap it smoothly and firmly around the patient's arm 5 cm just above elbow. Tuck the end in neatly .
3. Find the brachial pulse with the fingers and place the over it.
4. Close the screw valve and inflate the cuff until the pulse disappears and above that about 20mm mercury.

Practical 2.indd 267 07/05/18 2:20 PM