- From the right side of the garment, machine over the tacking line from one end up to its midpoint.
- Keep the machine needle in the fabric, raise the pressure foot and move the fullness backward out to prevent fold created on the placket.
- Lower the presser foot and stitch along the opposite end of the opening.
- Press the seam edges towards the placket strip and fold under the free edge of the strip of 0.25 cm and crease.
- Fold the strip over the seam edge and hem it along the stitching line.
- Fold the strip under on the overlap section and tack it close to the seam.
- Tacking should be removed after fixing the fasteners.

### 12.4.2.2 Bound and Faced Placket or Two-Piece Placket

As the name indicates, this is done with two pieces of fabrics. This placket is commonly used skirts, petticoats and back opening dresses. The overlap and under lap sides are finished with facing and binding respectively (Figure 12.25).




Figure 12.25 Bound and Faced Placket

**Method of Sewing Bound and Faced Placket**

- Cut two separate strips of fabric, measuring 8 cm width for the overlap and the other with 6 cm width for the under lap.
- The length of the strips should be 2.5 cm more than the length of the placket opening.
- The overlap and under lap sides are finished with the narrow and wide strips respectively.
- Care should be taken to maintain the stitching line of the seam along with the strips stitching line.
- The one inch extra length of the strips should extend below the placket opening.
- Crease the strip back over the seam and turn the free edges under the wrong side of the garment hem and finish the under lap.
- The completed bound side of placket should be 0.25 cm wide.
- Turn the overlap strip over completely to the wrong side making 0.25 cm fold on the wrong side of the garment and hem neatly.
- Finish the placket by a row hand stitches on the wrong side catching the under and overlap together.

### 12.4.2.3 Miter Placket

Miter placket is mainly used in men's shirts, sleeve opening and on neck openings for children's garments where strength is the major requirement. It is also called as tailored placket (Figure 12.26).

**Method of Sewing Miter Placket**

- Prepare a strip on straight grain measuring 7 cm wide and exact length



TDD_Final_Chapter12.indd 134 21-02-2019 12.35.49 PM