- Trim the extra material, turn hem right side out and press.
- Fold in seam allowances along stitching and press. Square corners must be mitered, rounded corners must be notched.
- Stitch the edge of the hem to the pocket by hand or top stitch from right side using machine.
- Pin the pocket to the garment, slip stitch around the pocket by hand or top stitch edges in place. Reinforce corners by back stitching or by stitching a small triangle or square. Both the top corners of the pockets must be reinforced properly to add strength.

13.3.2.2 Inseam Pocket

In seam pockets are sewn along the side seams of the garment. These pockets are made on the left side of the garment. These pockets are generally stitched in boy's shorts, girl's pant, pajama and kurtas. It can be cut as part of the garment front and back or it can be cut from a separate pattern piece and stitched to the seam. If the outer fabric is bulky or heavy, the pocket pieces can be cut from lining fabric (Figure 13.24).




Figure 13.24 Inseam Pocket

Method of Sewing Inseam Pockets

- Take two pairs of pocket pieces in the main fabric or plain fabric.
- Finish all the edges of pocket pieces.
- Stitch pocket pieces to front and back opening, right sides together. Press seam allowances toward pocket pieces.
- Pin the garment front and the garment back, matching at seam line and pocket.
- Stitch directionally along seam and around pocket in one step. Use reinforcement stitches. Press seam allowance flat.
- Turn the pocket toward the front of the garment. Piping material would be effective. Buttons may be fixed in groups to create design interest.
- Seams can be finished if necessary.

13.3.2.3 Slash Pocket

Slash pocket is a pocket suspended on the wrong side of the garment. A finished slit is seen on the right of the garment. It serves as pocket opening. There are three types of slash pockets namely, bound pocket, welt pocket and flap pocket.

- In bound pocket the edges are slashed and finished with binding. This is even in width.
- In case of welt pocket the binding are wider at the front, extending above the pocket opening.
- There is a flap attached over the bound or welt pocket. This is called flap pocket (Figure 13.25).




Figure 13.25 Slash Pocket

TDD_Final_Chapter13.indd 158 21-02-2019 12.48.02 PM