



- 3** **Fold the two inside pockets** right side to right side along the fold lines marked on the diagrams, then pin. Sew around the raw edges leaving a 1cm ($\frac{1}{2}$ in) seam allowance. Leave a 7.5cm (3in) gap in the seam. Turn each pocket to the right side through the gap. Use a pin to pull out the corners (see step 5, p.192), then iron the pockets.



- 4** **Make a small box pleat** in the middle of each pocket, following the instructions on page 227. Pin each pocket in position as marked on the diagrams, right side up on the right side of the bag lining. Pin the smaller pocket to the lining of the bag front and the larger pocket to the lining of the bag back/flap.



- 5** **Attach the pockets** to the lining by stitching along the middle stitch line of each box pleat, then around the bottom of each pocket and around the edges, leaving the top open. Each pocket now has two sections.



- 6** **Fold the two side pockets right side to right side** along the fold lines marked on the diagrams. Pin, then stitch the raw short edges together. Turn the pockets to the right side, then iron. Make a small box pleat in each pocket following steps 1–5 on page 227, then align the long edges of the pockets with the edges of one of the side/bottom strips, as shown. Pin, leaving the pockets open along one short edge. The openings should each be 11.5cm ($4\frac{1}{2}$ in) from the corresponding end of the side/bottom strip. Attach the pockets by stitching around the sides and the bottom.