



- 11** Lay the two side/bottom strips together, right side to right side, sandwiching the back of the bag between them. The side pockets should face the right side of the back of the bag. Pin together, leaving a 1cm ($\frac{1}{2}$ in) seam allowance above the notch.



- 12** Stitch through all three layers to 1cm ($\frac{1}{2}$ in) from the bottom edge of the back. With the bag still under the presser foot, snip at an angle 1cm ($\frac{1}{2}$ in) into the side/bottom strips only. Do not snip through the back of the bag. The snip line is marked above in red, for reference.



- 13** Turn the side/bottom strips at the snips so their edges align with the bottom edge of the bag, then pin, as shown. Pivot the entire bag under the presser foot, then sew along the bottom edge to the next corner. Snip again as in step 12, turn the strips again, then pin them along the third side. Pivot the bag again, then sew along the third side.



- 14** Stitch each end of the strap right side to right side to each short edge of the side/bottom strip that you attached the side pockets to in step 6. Turn down the short edges of the other side/bottom strip by 1cm ($\frac{1}{2}$ in) and iron. These will be finished by hand in step 17.