




- 11** **Attach a free-motion foot** or a darning foot to your sewing machine. With the quilt face up, start in one corner and work your way along the edge, stitching all three layers together. You can stitch any pattern you like. As you sew, keep your speed constant, hold the quilt firmly, and move it evenly under the foot. Once you have quilted the entire top, carefully remove the tacking stitches and trim the wadding and backing fabric to the same size as the quilt top.



- 13** **Wrap the bias binding** around the edge of the quilt to the back, folding its raw edge under by 5mm ($\frac{1}{4}$ in). Hand-stitch the binding in place to the back of the quilt only, weaving your needle back and forth. Alternatively, you can machine-stitch the binding in place. Pin the folded edge to the quilt first, then machine-stitch carefully from the front so that the stitches sit in the “ditch” created by the seam that attached the binding in step 12.



- 12** **Starting in the middle of one side** of the quilt, pin the edge of the bias binding along the edge of the quilt, right side to right side, turning over a small hem on the short end of the bias binding first. Sew the quilt and bias binding together leaving a 1cm ($\frac{1}{2}$ in) seam allowance. When you reach a corner, mitre the bias binding so it lies flat. To mitre the bias binding, remove the quilt from under the presser foot without cutting the threads. Fold the bias binding over and to the right, making a diagonal fold at the corner. Keeping that diagonal fold in place, fold the bias binding back over to the left. Pin the corner, turn the quilt, then pin the binding along the next side and sew it to the quilt as before. Repeat until all four sides have bias binding.

