Following Litestream's installation instructions,[123] we first need to install Litestream. SSH into your host, and run the following commands:

```
apt-get update
apt-get install -y wget
export
LITESTREAM=https://github.com/benbjohnson/litestream/releases/download
wget $LITESTREAM/v0.3.13/litestream-v0.3.13-linux-amd64.deb
dpkg -i litestream-v0.3.13-linux-amd64.deb
rm litestream-v0.3.13-linux-amd64.deb
```

Now find the `ACCESS_KEY_ID`, `SECRET_ACCESS_KEY`, `ENDPOINT_URL`, `REGION`, and `BUCKET_NAME` in your password manager. Then run `nano /etc/litestream.yml`. Replace the file with the following, substituting in the values you found in your password manager:

```
# This is the configuration file for litestream.
#
# For more details, see: https://litestream.io/reference/config/
#
dbs:
  - path: /var/lib/docker/volumes/work_storage/production.sqlite3
    replicas:
      - type: s3
        access-key-id: ACCESS_KEY_ID
        secret-access-key: SECRET_ACCESS_KEY
        endpoint: ENDPOINT_URL
        region: REGION
        bucket: BUCKET_NAME
        path: storage/production.sqlite3
```

Exit nano by pressing Ctrl-X, and then press Y to save the file.

Now start the Litestream service:

```
systemctl enable litestream
systemctl start litestream
```

Once configured, Litestream is pretty much set and forget. It will back up your database after every write and can be used to restore your database to a