development mode by default. Otherwise, all autoloading happens only once. All elements of this array must also be in `autoload_paths`. Default is an empty array.

- `config.autoload_paths` accepts an array of paths from which Rails will autoload constants. Default is all directories under `app`.
- `config.cache_classes` controls whether or not application classes and modules should be reloaded on each request. Defaults to false in development mode, and true in test and production modes.
- `config.action_view.cache_template_loading` controls whether or not templates should be reloaded on each request. Defaults to whatever is set for `config.cache_classes`.
- `config.beginning_of_week` sets the default beginning of week for the application. Accepts a valid week day symbol (e.g. `:monday`).
- `config.cache_store` configures which cache store to use for Rails caching. Options include one of the symbols `:memory_store`, `:file_store`, `:mem_cache_store`, `:null_store`, or an object that implements the cache API. Defaults to `:file_store` if the directory `tmp/cache` exists, and to `:memory_store` otherwise.
- `config.colorize_logging` specifies whether or not to use ANSI color codes when logging information. Defaults to true.
- `config.consider_all_requests_local` is a flag. If true then any error will cause detailed debugging information to be dumped in the HTTP response, and the `Rails::Info` controller will show the application runtime context in `/rails/info/properties`. True by default in development and test environments, and false in production mode. For finer-grained control, set this to false and implement `local_request?` in controllers to specify which requests should provide debugging information on errors.
- `config.console` allows you to set class that will be used as console you run `rails console`. It's best to run it in `console` block:

```
console do
  # this block is called only when running console,
  # so we can safely require pry here
  require "pry"
  config.console = Pry
end
```

- `config.dependency_loading` is a flag that allows you to disable constant autoloading setting it to false. It only has effect if `config.cache_classes` is true, which it is by default in production mode.
- `config.eager_load` when true, eager loads all registered `config.eager_load_namespaces`. This includes your application, engines, Rails frameworks and any other registered namespace.
- `config.eager_load_namespaces` registers namespaces that are eager loaded when `config.eager_load` is true. All namespaces in the list must respond to the `eager_load!`method.
- `config.eager_load_paths` accepts an array of paths from which Rails will eager load on boot if cache classes is enabled. Defaults to every folder in the `app` directory of the application.
- `config.encoding` sets up the application-wide encoding. Defaults to UTF-8.
- `config.exceptions_app` sets the exceptions application invoked by the ShowException middleware when an exception happens. Defaults to `ActionDispatch::PublicExceptions.new(Rails.public_path)`.
- `config.file_watcher` the class used to detect file updates in the filesystem when `config.reload_classes_only_on_change` is true. Must conform to `ActiveSupport::FileUpdateChecker` API.
- `config.filter_parameters` used for filtering out the parameters that you don't want shown in the logs, such as passwords or credit card numbers. New applications filter out passwords by adding the