    - `:user_name` - If your mail server requires authentication, set the username in this setting.
    - `:password` - If your mail server requires authentication, set the password in this setting.
    - `:authentication` - If your mail server requires authentication, you need to specify the authentication type here. This is a symbol and one of `:plain`, `:login`, `:cram_md5`.
- `config.action_mailer.sendmail_settings` allows detailed configuration for the `sendmail` delivery method. It accepts a hash of options, which can include any of these options:
    - `:location` - The location of the sendmail executable. Defaults to `/usr/sbin/sendmail`.
    - `:arguments` - The command line arguments. Defaults to `-i -t`.
- `config.action_mailer.raise_delivery_errors` specifies whether to raise an error if email delivery cannot be completed. It defaults to true.
- `config.action_mailer.delivery_method` defines the delivery method and defaults to `:smtp`. See the configuration section in the Action Mailer guide for more info.
- `config.action_mailer.perform_deliveries` specifies whether mail will actually be delivered and is true by default. It can be convenient to set it to false for testing.
- `config.action_mailer.default_options` configures Action Mailer defaults. Use to set options like `from` or `reply_to` for every mailer. These default to:
```
mime_version:  "1.0",
charset:       "UTF-8",
content_type: "text/plain",
parts_order:  ["text/plain", "text/enriched", "text/html"]
```
- Assign a hash to set additional options:

```
config.action_mailer.default_options = {
  from: "noreply@example.com"
}
```
- `config.action_mailer.observers` registers observers which will be notified when mail is delivered.
```
config.action_mailer.observers = ["MailObserver"]
```
- `config.action_mailer.interceptors` registers interceptors which will be called before mail is sent.
```
config.action_mailer.interceptors = ["MailInterceptor"]
```
- `config.action_mailer.preview_path` specifies the location of mailer previews.
```
config.action_mailer.preview_path =
"#{Rails.root}/lib/mailer_previews"
```
- `config.action_mailer.show_previews` enable or disable mailer previews. By default this is `true` in development.
```
config.action_mailer.show_previews = false
```

3.11 Configuring Active Support

There are a few configuration options available in Active Support:

- `config.active_support.bare` enables or disables the loading of `active_support/all`when booting Rails. Defaults to `nil`, which means `active_support/all` is loaded.
- `config.active_support.test_order` sets the order that test cases are executed. Possible values are `:sorted` and `:random`. Currently defaults to `:sorted`. In Rails 5.0, the default will be changed to `:random` instead.
- `config.active_support.escape_html_entities_in_json` enables or disables the escaping of HTML entities in JSON serialization. Defaults to `false`.