```
logfile = pgbouncer.log
pidfile = pgbouncer.pid
admin_users = app_user
```

With PgBouncer configured, you're ready to connect it to the Rideshare database.

Try connecting to PostgreSQL via pgbouncer by running the following psql command with a connection string from your Terminal.

sh/pgbouncer_psql_connection_string.sh

```
# pgbouncer user, password, created earlier
# port=6432
psql "postgresql://app_user:insecurepwd@localhost:6432/rideshare_development"
```

PgBouncer acts transparently as a proxy and is compatible with psql. View some information about PgBouncer by running these commands:

sh/pgbouncer_connect_explore.sh

```
# Special administration "pgbouncer" database
psql -p 6432 -U app_user pgbouncer

# List commands available from pgbouncer prompt
SHOW help;
```

This brings up a command line interface like psql where you can run various commands. PgBouncer can be restarted using a rolling restart. Refer to the documentation for more information.

sh/restart_pgbouncer.sh

```
# Note that -R/--reboot is deprecated. Refer to documentation
# for a rolling restart.
pgbouncer --reboot /usr/local/etc/pgbouncer.ini --daemon
```

PgBouncer supports SQL formatted commands. Try running some of the following commands while connected to the special pgbouncer database.

sql/pgbouncer_commands.sql

```
SHOW help;
SHOW clients;
SHOW databases; -- Review `pool_size`, `pool_mode`, etc.
```

If you ran show databases;, one of the options you'll see is the Pool Mode. What's that all about?

Choosing A PgBouncer Pooling Mode

PgBouncer supports various *Pool Modes*. The Pool Mode specifies how a server connection may be reused by clients.