```
        }
    }
```

To get the tab bar controller on the screen, we need to assign it to the window. Assign the `rootViewController` to the `HotwireTabBarController` instance. Finally, load the tabs from our `HotwireTab` extension via `load()`.

ch04_05/ios/App/Delegates/SceneDelegate.swift

```
    import HotwireNative
    import UIKit

    let baseURL = URL(string: "http://localhost:3000")!

    class SceneDelegate: UIResponder, UIWindowSceneDelegate {
        var window: UIWindow?

        private let tabBarController = HotwireTabBarController()

        func scene(
            _ scene: UIScene,
            willConnectTo session: UISceneSession,
            options connectionOptions: UIScene.ConnectionOptions
        ) {
»           window?.rootViewController = tabBarController
»           tabBarController.load(HotwireTab.all)
        }
    }
```

Now the iOS app has a way to navigate between the pages we removed in the previous chapter when we hid the web-based navigation bar. And iOS users will immediately be more familiar with your app because you're using platform-specific, native controls.