ch07_05/rails/app/javascript/controllers/bridge/button_controller.js

```
  import { BridgeComponent } from "@hotwired/hotwire-native-bridge"

  export default class extends BridgeComponent {
    static component = "button"

»   connect() {
»     super.connect()
»   }
  }
```

To communicate with the native component, we'll use the `send()` function from `BridgeComponent`, which takes three parameters:

1. The name of the message to send
2. An options *object* (or "hash", in Ruby terms)
3. An optional callback function

At the end of `connect()`, call `send()` with "connect" as the first parameter, followed by an empty options object and an empty callback function.

ch07_06/rails/app/javascript/controllers/bridge/button_controller.js

```
  import { BridgeComponent } from "@hotwired/hotwire-native-bridge"

  export default class extends BridgeComponent {
    static component = "button"

    connect() {
      super.connect()

»     this.send("connect", {}, () => {
»     })
    }
  }
```

We'll come back and add more to this later in the chapter. But for now, let's create the third building block—the native counterpart—to make sure everything is wired up correctly between the web side and the client side.