Create a Native Component

In the iOS app, create a new directory under `App` and name it Components. Inside, create a new Swift file named `ButtonComponent.swift`. Replace the contents with the following:

ch07_07/ios/App/Components/ButtonComponent.swift

```
import HotwireNative
import UIKit

class ButtonComponent: BridgeComponent {
}
```

Next, identify this component as “button”, just like on the web.

ch07_08/ios/App/Components/ButtonComponent.swift

```
import HotwireNative
import UIKit

class ButtonComponent: BridgeComponent {
»   override class var name: String { "button" }
}
```

Unlike the web, we have to manually register this component with Hotwire Native. Open `AppDelegate.swift` and register this bridge component after setting up the path configuration.

ch07_09/ios/App/Delegates/AppDelegate.swift

```
import HotwireNative
import UIKit

@main
class AppDelegate: UIResponder, UIApplicationDelegate {
    func application(
        _ application: UIApplication,
        didFinishLaunchingWithOptions launchOptions:
```