


Remove the Component on Disconnect

The component exists in the native part of the screen, the navigation bar. But when we sign out, only the web content is reloaded. There's no way for the component to know the button shouldn't be there anymore.

We can fix this by manually removing the button when the Stimulus controller disconnects.[46] One way for `disconnect()` to be called is when the element's `data-controller` attribute is removed. And the page is refreshed when we sign out, removing the element.

Start by adding a `disconnect()` function in `button_controller.js` that sends the "disconnect" message to the app.

ch07_20/rails/app/javascript/controllers/bridge/button_controller.js

```
import { BridgeComponent } from "@hotwired/hotwire-native-bridge"

export default class extends BridgeComponent {
  static component = "button"
```