II. Barrier Methods

Condoms:

Types: -Latex (plain or treated with spermicide)

- The spermicide will immobilize or kills sperm providing added protection if breakage or leaks occur.

Direction of use:

- The condom should be applied before vaginal penetration and should cover the entire length of the erected penis. Adequate lubrication should be used and the condom should be removed immediately after ejaculation and disposed properly.

Advantages	Disadvantages
• Fairly effective in preventing pregnancy • Only contraceptive method that provides protection against STD's.	• High failure rate 3 to 15 per 100 women. • Only synthetic condom can provide protection against HIV and HBV's • If either partners has latex allergy, a non-latex product should be used.

Diaphragm:

Advantages	Disadvantages
• Effective in preventing pregnancy if used properly and provide same protection against STD's • Decreased risk of cervical cancer	• High failure rate • Slight risk of toxic shock syndrome. • Increased risk of UTI • It requires initial fitting.

Types:

i) flat spring ii) Coil spring iii) Arching spring

The diaphragm should lie just posterior to symphysis pubis and deep into the cul-de-sac, so that the cervix is completely covered and behind the centre of the membrane. Spermicide should be applied before each coital act. The diaphragm should left in place for a maximum of 8 hrs after the last coital act.

Cervical Cap

- It is a dome shaped cup that fits over the cervix.
- It cannot be left in the cervix for more than 48 hours.
- Only women with normal pap smear can use.

Spermicide

They are agents that cause destruction of the sperm cell membrane; thereby affecting mobility.

- Aerosol foams
- Creams and Jellies
- Vaginal suppositories
- Films & sponges

All contain spermicidal agents usually nontoxic.

Advantages	Disadvantages
• Serves as a lubricant and also provides some protection against STD's • Reduced risk of cervical neoplasia	• High failure rate • Effective for only 1-2 hours

III. Iucd- Intra Uterine CONTRACEPTIVE Devices

Modern Methods

They are flexible plastic device medicated with slowly released hormones. Copper – released devices interferes with the ability of sperm to pass through the uterine cavity.

Unit_7_Midwifery_Gen_Nur.indd 169 09-03-2020 14:51:13