Our interest right now is Ruby 3.2.0, which we can install with the command rbenv install 3.2.0. If you don't see the most current version of Ruby on the list, and you've installed rbenv previously, you may get instructions on how to update ruby-build to get newer Ruby versions in your list. Note that none of the rbenv commands require us to have superuser access or to use sudo. One of the joys of the Ruby version managers, including rbenv, is that they do everything inside your home directory—you don't have have any special system privileges to install or use new Ruby versions.

```
$ rbenv install 3.2.0
To follow progress, use
'tail -f <REDACTED>'
or pass --verbose
Installing openssl-3.0.7...
Installed openssl-3.0.7 to /Users/noel/.rbenv/versions/3.2.0

Installing ruby-3.2.0...
ruby-build: using readline from homebrew
ruby-build: using gmp from homebrew
Installed ruby-3.2.0 to /Users/noel/.rbenv/versions/3.2.0
```

Your output may be slightly different, depending on the exact version number and whether you are re-installing the Ruby version.

We can verify that the Ruby version has been installed with rbenv versions, for example

```
$ rbenv versions
* system
  3.2.0
```

The system here is the pre-defined Ruby for the operating system if such a thing exists, and the asterisk shows which version is currently active.

An important step: after you install a new ruby via rbenv, you must run the command rbenv rehash. This command produces no output, but it does enable rbenv to use the newly installed Ruby.

Right now, the system Ruby is still active. Let's change that.

Switching Rubies with rbenv

This is where we start to see the payoff. Once different Ruby versions are installed, and rbenv rehash has been called, Rbenv allows us multiple ways to switch the Ruby version we are using.

The command rbenv local <version> changes the Ruby version for the directory you are in:

```
$ ruby --version
ruby 2.6.10p210 (2022-04-12 revision 67958) [universal.arm64e-darwin22]

$ rbenv local 3.2.0

$ ruby --version
ruby 3.2.0 (2022-12-25 revision a528908271) [arm64-darwin22]
```

This setting for the directory persists even if you leave the directory and come back. (If you don't want the change to persist beyond the current session, you can use rbenv shell <version>) instead of rbenv local.