are an integral part of drafting. Fashion designing has come a long way in style, pattern making techniques and manufacture of garments. The most common method of pattern making is described below. It is also known as tailor's pattern making technique. The measurement mentioned in the pattern is suitable for normal adult (20-21 years). The measurements for marking points at shoulder or armhole can be reduced or increased depending upon age or type of figure of the individual.

The most common method Back Bodice Pattern of pattern making is described below. It is also known as tailors pattern making techniques. (The measurement mention in the pattern is suitable for a normal adult (20-21 years). The measurement for marking points at shoulder as armhole can be reduced or increased depending upon age or type of the figure of the individual.

8.3 Back Bodice Pattern

- Draw a rectangle using the following measurements. Be sure to leave at least three centimetre margin around the rectangle. Point A-B = 1/4 bust circumference- 1 cm + 0.5 cm (for ease). Points A-C = back length. Now close of the rectangle making sure it is perfectly squared (each corner should be 90° angle)
- From points C-E and D-F mark the side length measurement connect points E and F with the straight line.
- From points A-H and E-G mark half the back width connect points H and G with the straight line.
- From point A-I mark down about 1.5 – 2 cms. From point A-J mark one tenth the waist measurements. Connect point I-J with a slight curve. This is the neck hole of the bodice.
- From point H down to K mark 4.5 cm. Draw a straight line from point J-K over marking K by 0.5 cm that slightly over so that it will be pointed at L.
- Mark a 3 cm from point G-M. Now connect points F, M and L with a curve. This is the armhole for your bodice.




Figure 8.1 Back Bodice Pattern

- From point C-N mark 9.5 cm
- From point N-O mark a perpendicular line 15 cms long. Mark 1.5 cm to either side of point N and connect both these points to point O with a straight line. This will be the back dart
- From point C-P mark 1/4th of waist measurements - 1 cm + 3 cm - 0.5 cm. Connect points F-P with a straight line.

XII TDD_English version CHAPTER 08.indd 108 1/13/2020 3:18:47 PM