- Mark 1.5 cms to either side of points O and connect both these points to point Q (waist dart).
- From point C-R apply 1/4th waist + 1 cm +3 cms + 0.5 cm. Connect R-F with a straight line.
- Connect L, I and F with a curve (armhole).
- Cut out the pattern except leave the 3cm margin at the top shoulder. Close the shoulder dart following the flap in the back towards the armhole. Tape it shut, then redraw the shoulder line. Cut straight across the new shoulder line.




Figure 8.5 Front Bodice Pattern Working

Sleeve

- A-B sleeve = sleeve length 7 1/2 inches (19 cms) to 7 3/4th inches (20 cms).
- A-C =4 1/2 inches (12 cms).
- Square points C and B to the right.
- A-D = 3/8 inch (1 cm).
- D-E =1/2 armhole measurement.
- B-F =1/2 lower arm girth + 3/8 inch (1 cm).
- Connect E-F and D-E.
- Divide line D-E into 4 equal parts and mark G, H, I.
- G-J raise 5/8 inch (1.5 cm).
- I-K lower 5/8 inch (1.5 cm). Connect D, J, H with a French curve.
- Connect E, L, H with a French curve (for front sleeve cap). H-L 1/4 inch = 10.5 cm.




Figure 8.6 Working Sleeve Pattern

- M centre of K and I. Connect J, L, M and E for back sleeve cap line with a dotted line.
- Cut off L-E and F-E. Open the sleeve and cut E, K, H to J for front sleeve pattern.
- After drafting the basic pattern check it correctly and accurately, especially the measurements and the parts of pattern pieces and then cut the basic pattern the following cutting line smoothly.

XII TDD_English version CHAPTER 08.indd 110 1/13/2020 3:18:47 PM