```
    environment:
      - POSTGRES_USER=user
      - POSTGRES_PASSWORD=password
      - POSTGRES_DB=polardb_catalog
```

❶ The Docker Compose syntax version

❷ The section containing all the containers to run

❸ The section describing the catalog-service container

❹ Catalog Service should start after the PostgreSQL database.

❺ The image used to run the container

❻ The name of the container

❼ The section listing the port mappings

❽ The section listing the environment variables

❾ A Paketo Buildpacks environment variable to configure the number of threads for memory calculation

❿ Enables the “testdata” Spring profile

The section describing the polar-postgres container

You might have noticed the presence of an additional environment variable for the Catalog Service container. In chapter 15, you’ll learn about the Java memory calculator provided by Paketo Buildpacks and how to configure CPU and memory for Spring Boot applications. For now, it’s enough to know that the `BPL_JVM_THREAD_COUNT` environment variable is used to configure the number of threads memory should be allocated for in the JVM stack. The default value for Servlet-based applications is 250. In chapter 3, we used a low value for the Tomcat thread pool, and it’s good to do the same for the JVM memory configuration to keep the container’s memory usage low locally. You’re going to deploy many containers throughout the book (both applications and backing services), and such configuration helps make that possible without overloading your computer.

Docker Compose configures both containers on the same network by default, so you don’t need to specify one explicitly, as you did previously.