We'll configure Keycloak through its Admin CLI, but you can achieve the same result by using the GUI available at http://localhost:8080. First, navigate to the folder where the Keycloak Admin CLI scripts are located:

```
$ cd /opt/keycloak/bin
```

The Admin CLI is protected by the username and password we defined in Docker Compose for the Keycloak container. We'll need to start an authenticated session before running any other commands:

```
$ ./kcadm.sh config credentials \
    --server http://localhost:8080 \     ❶
    --realm master \                     ❷
    --user user \                        ❸
    --password password                  ❹
```

❶ Keycloak runs on port 8080 inside the container.

❷ The default realm configured in Keycloak

❸ The username we defined in Docker Compose

❹ The password we defined in Docker Compose

TIP You should keep the current Terminal window open until you're done configuring Keycloak. If at any point the authenticated session expires, you can always start a new one by running the previous command.

At this point, you can go ahead and create a new security realm where all the policies associated with Polar Bookshop will be stored:

```
$ ./kcadm.sh create realms -s realm=PolarBookshop -s enabled=true
```

11.2.2 Managing users and roles

We'll need some users to test different authentication scenarios. As anticipated in chapter 2, Polar Bookshop has two types of users: customers