FUNCTION DETAILS

There are five functions, including the constructor:

- `constructor()`--The constructor function is called when the smart contract is deployed. The account number that deploys the contract is that of the chairperson. The constructor takes the number of proposals to be voted on as a parameter. It initializes the data elements and the state of the voting phase (to `Regs` from `Init`).
- `changeState()`--This function changes the state of the voting to the correct phase. It can be executed only by the chairperson, and the parameter value has to be in the correct order (1, 2, 3). Execute this function from the chairperson account's address before transitioning to `register()`, `vote()`, and `reqWinner()` for the first time. The statement `if (x < state) revert();` works only for simple state advancement. This basic version of state change is improved to a generic version in chapter 4.
- `register()`--This function should be executed only by the chairperson account; otherwise, it will revert and won't be executed. It will also revert if the `voted` Boolean variable is `true` and if the `state` is not `Phase.Regs`.
- `vote()`--This function can execute only during the voting phase (`Phase.Vote`). This rule is enforced by the modifier (rule) `validPhase(Phase.Vote)`. You can observe the validation of the "one person-one vote" rule and the proposal number. (When the voting period ends, the `state` is changed to `Phase.Done` by the chairperson.)