- Worker (receiver) address in the migrations/2_deploy_contracts.js (listing 8.5)
- Setup escrow deposit or channel balance in migrations/2_deploy-contracts.js (listing 8.5)
- HDWalletProvider address with Infura endpoint and account mnemonic of the organizer in truffle-config.js (listing 8.6)

Listing 8.5 2_deploy_contracts.js

```
var MPC = artifacts.require("MPC");

module.exports = function(deployer,networks,accounts) {
  ...
  if(networks=='ropsten'){
    var receiver='0xd47fEd9f17622d64e154C3af70eE18C4920Bc9B5';    ❶
    var balance=1000000000000000000;                              ❷
    deployer.deploy(MPC,receiver,{value:balance});
  }
};
```

❶ Change the worker's account address from MPCEnv.txt.

❷ Channel balance or escrow deposit 1ETH = 1000000000000000000

The parameters you set in 2_deploy_contracts.js, the receiver or worker's address, and the channel balance or escrow deposit are passed on to the smart contract when the constructor deploys it. That sets up the channel and the value the channel holds for micropayments. This value of channel balance is displayed in the web interface along with the balances of the organizer and the worker. You have only 1 ETH available for work, so the micropayments cumulatively have to be within this amount. Save the updated 2_deploy_contracts.js file.