It receives a `trackVisibility` prop that determines whether the autoscrolling behavior should be enabled. The component uses the `useIsAtBottom` hook to check whether it is at the bottom of the viewport and the `useInView` hook to determine whether it is currently in view. If `trackVisibility` is `true` and the component is at the bottom and not in view, the component smoothly scrolls itself into view using the `scrollIntoView` method.

Figure 2.6 shows how this interaction works. Of course, this is not the only way to implement autoscrolling, but it works quite well in most use cases.




Figure 2.6 The `<Autoscroll/>` component works by triggering a scroll to the bottom of the page. The criteria that trigger the autoscrolling behavior are as follows: the `trackVisibility` prop is set to `true`, the component is at the bottom of the viewport (determined by the `useIsAtBottom` hook), and the component is not currently in view (determined by the `useInView` hook).

You might notice that with the current `AutoScroll` component, if the conversation gets very long, it always forces the view to the bottom when new messages arrive. This can