This is an atomic store operation for the memory location comprising `*this`.

Std::Atomic_Store Nonmember Function

Atomically stores a new value in an `atomic<BaseType>` instance.

Declaration

```
template<typename BaseType>
void atomic_store(volatile atomic<BaseType>* p, BaseType new_value)
    noexcept;
template<typename BaseType>
void atomic_store(atomic<BaseType>* p, BaseType new_value)
noexcept;
```

Effects

```
p->store(new_value);
```

Std::Atomic_Store_Explicit Nonmember Function

Atomically stores a new value in an `atomic<BaseType>` instance.

Declaration

```
template<typename BaseType>
void atomic_store_explicit(
    volatile atomic<BaseType>* p, BaseType new_value, memory_order
order)
    noexcept;
template<typename BaseType>
void atomic_store_explicit(
    atomic<BaseType>* p, BaseType new_value, memory_order order)
noexcept;
```

Effects

```
p->store(new_value,order);
```

Std::Atomic::Exchange Member Function