```
    volatile atomic<integral-type>*,integral-type ) noexcept;
integral-type  atomic_fetch_xor(
    atomic<integral-type>*,integral-type ) noexcept;
integral-type  atomic_fetch_xor_explicit(
    volatile atomic<integral-type>*,integral-type , memory_order)
noexcept;
integral-type  atomic_fetch_xor_explicit(
    atomic<integral-type>*,integral-type , memory_order) noexcept;
```

Those operations that are also provided by the primary template (see D.3.8) have the same semantics.

Std::Atomic<Integral-Type>::Fetch_Add Member Function

Atomically loads a value and replaces it with the sum of that value and the supplied value `i`.

Declaration

```
integral-type  fetch_add(
    integral-type i,memory_order order = memory_order_seq_cst)
    volatile noexcept;
integral-type  fetch_add(
    integral-type i,memory_order order = memory_order_seq_cst)
noexcept;
```

Effects

Atomically retrieves the existing value of `*this` and stores *old-value* `+ i` in `*this`.

Returns

The value of `*this` immediately prior to the store.

Throws

Nothing.