Atomically loads a value and replaces it with the sum of that value and the supplied value `i`.

Declaration

```
integral-type  fetch_sub(
    integral-type i,memory_order order = memory_order_seq_cst)
    volatile noexcept;
integral-type  fetch_sub(
    integral-type i,memory_order order = memory_order_seq_cst)
noexcept;
```

Effects

Atomically retrieves the existing value of `*this` and stores *old-value* `- i` in `*this`.

Returns

The value of `*this` immediately prior to the store.

Throws

Nothing.

Note

This is an atomic read-modify-write operation for the memory location comprising `*this`.

Std::Atomic_Fetch_Sub Nonmember Function

Atomically reads the value from an `atomic<`*integral-type*`>` instance and replaces it with that value minus the supplied value `i`.

Declaration