```
integral-type  atomic_fetch_sub(
    volatile atomic<integral-type>* p, integral-type i) noexcept;
integral-type  atomic_fetch_sub(
    atomic<integral-type>* p, integral-type i) noexcept;
```

Effects

```
return p->fetch_sub(i);
```

Std::Atomic_Fetch_Sub_Explicit Nonmember Function

Atomically reads the value from an `atomic<`*integral-type*`>` instance and replaces it with that value minus the supplied value `i`.

Declaration

```
integral-type  atomic_fetch_sub_explicit(
    volatile atomic<integral-type>* p, integral-type i,
    memory_order order) noexcept;
integral-type  atomic_fetch_sub_explicit(
    atomic<integral-type>* p, integral-type i, memory_order order)
    noexcept;
```

Effects

```
return p->fetch_sub(i,order);
```

Std::Atomic<Integral-Type>::Fetch_Sub Member Function

Atomically loads a value and replaces it with the bitwise-and of that value and the supplied value `i`.

Declaration

```
integral-type  fetch_and(
    integral-type i,memory_order order = memory_order_seq_cst)
    volatile noexcept;
integral-type  fetch_and(
    integral-type i,memory_order order = memory_order_seq_cst)
noexcept;
```

Effects