Nothing.

Std::Recursive_Mutex::Lock Member Function

Acquires a lock on a `std::recursive_mutex` object for the current thread.

Declaration

```
void lock();
```

Effects

Blocks the current thread until a lock on `*this` can be obtained.

Postconditions

`*this` is locked by the calling thread. If the calling thread already held a lock on `*this`, the lock count is increased by one.

Throws

An exception of type `std::system_error` if an error occurs.

Std::Recursive_Mutex::Try_Lock Member Function

Attempts to acquire a lock on a `std::recursive_mutex` object for the current thread.

Declaration

```
bool try_lock() noexcept;
```

Effects

Attempts to acquire a lock on `*this` for the calling thread without blocking.