Declaration

```
template<typename Callable,typename Args...>
explicit thread(Callable&& func,Args&&... args);
```

Preconditions

`func` and each element of `args` must be `MoveConstructible`.

Effects

Constructs a `std::thread` instance and associates it with a newly created thread of execution. Copies or moves `func` and each element of `args` into internal storage that persists for the lifetime of the new thread of execution. Performs *INVOKE (copy-of-*`func`*,copy-of-*`args`*)* on the new thread of execution.

Postconditions

For a newly constructed `std::thread` object `x`, `x.get_id()!=id()`.

Throws

An exception of type `std::system_error` if unable to start the new thread. Any exception thrown by copying `func` or `args` into internal storage.

Synchronization

The invocation of the constructor happens-before the execution of the supplied function on the newly created thread of execution.

Std::Thread Move-Constructor

Transfers ownership of a thread of execution from one `std::thread` object to a newly created `std::thread` object.