7.2 Akka configuration

Okay, you've seen how you can use the configuration library for your application's properties, but what do you need to do when you want to change some of Akka's configuration options? How is Akka using this library? It's possible to have multiple `ActorSystem`s with their own configuration. When no configuration is present at creation, the `ActorSystem` creates the configuration using the defaults:

```
val system = ActorSystem("mySystem")    ❶
```

❶ ConfigFactory.load() is used internally to create a default config for the config argument that is omitted here.

But it's also possible (and useful) to supply the configuration while creating an `ActorSystem`. Here's a simple way to accomplish this:

```
val configuration = ConfigFactory.load("myapp")        ❶
val systemA = ActorSystem("mySystem",configuration)    ❷
```

❶ Loads the configuration, providing a name

❷ Passes it to the ActorSystem constructor

The configuration is within your application in the settings of the `ActorSystem`. This can be accessed within every actor. Here, the `applicationDescription` gets its value from the property `MyAppl.name`:

```
val mySystem = ActorSystem("myAppl")
val config = mySystem.settings.config                          ❶
val applicationDescription = config.getString("MyAppl.name")   ❷
```