recover and return to the cluster; this is not allowed for security reasons.

To start the node again, you can run the `Main` class in chapter08a, which contains the same code you pasted to start the node:

```
import akka.actor.typed.ActorSystem
import akka.actor.typed.scaladsl.Behaviors

object Main extends App {

  ActorSystem(Behaviors.empty, "words")
}
```

To start a node with this `Main`, enter the following in the command line:

```
sbt -DPORT=2552 chapter08a/run
```

Note that the port here is 2552. Feel free to change it depending on what ports are available to you.

8.2.6 Downing a reachable node

It is possible to shut down a node from any node in the cluster by sending an `akka.cluster.type.Down` message. The following listing shows how to shut down node 1 from the REPL by creating the address that points to node 1 and sending a down message to the cluster manager.

Listing 8.3 Taking down seed node 1 manually

```
scala> import akka.actor.Address
scala> import akka.cluster.typed.{ Cluster, Down}
scala> val address = Address("akka", "words", "127.0.0.1",2551)
```