By default, only the getters are available. All operations that have side effects—that is, that change the states of nodes—are available only if the following is set: `akka.management.http.route-providers-read-only = false`.

You can use the getter `127.0.0.1:8558/cluster/members` to get the status of your cluster. You should get something similar to the following listing.

Listing 8.4 Status of the cluster

```
{
  "leader": "akka://words@127.0.0.1:2551",          ❶
  "members": [                                      ❷
    {
      "node": "akka://words@127.0.0.1:2551",
      "nodeUid": "-4766935219030085168",
      "roles": [
        "seed",
        "dc-default"
      ],
      "status": "Up"
    },
    {
      "node": "akka://words@127.0.0.1:2552",
      "nodeUid": "-6827274415967400234",
      "roles": [
        "seed",
        "dc-default"
      ],
      "status": "Up"
    }
  ],
  "oldest": "akka://words@127.0.0.1:2551",          ❶
  "oldestPerRole": {
    "seed": "akka://words@127.0.0.1:2551",
    "dc-default": "akka://words@127.0.0.1:2551"
  },
  "selfNode": "akka://words@127.0.0.1:2551",
  "unreachable": []                                 ❸
}
```

❶ The leader is the oldest.