You need to create a `Role` with the appropriate permission and bind it to a Kubernetes service account (SA). Every time you run `kubectl` to access the cluster—the Kubernetes API server—you do so through a user account. However, when a process in a pod calls the Kubernetes API server, such as your app, it does so via the default SA, which is called `default`.

Adding a role and binding it to a SA allows the Akka cluster to fetch, watch, and list the pods. The `Role` and `RoleBinding` you need are shown in the following listing.

Listing 13.6 `Role` and `RoleBinding` to allow the cluster to get, watch, and list pods

```
kind: Role
apiVersion: rbac.authorization.k8s.io/v1
metadata:
  name: pod-reader
rules:
- apiGroups: [""] # "" indicates the core API group
  resources: ["pods"]                                    ❶
  verbs: ["get", "watch", "list"]                        ❷
---
kind: RoleBinding
apiVersion: rbac.authorization.k8s.io/v1
metadata:
  name: read-pods
subjects:
- kind: ServiceAccount
  name: default                                          ❸
roleRef:
  kind: Role
  name: pod-reader                                       ❹
  apiGroup: rbac.authorization.k8s.io
```

❶ Role permissions refer to pods.

❷ Queries available on the resources

❸ Binds to the default service account

❹ Binds it to the role