```
        for (var attr : claims.getClaims().keySet()) {    #C
            if (ignore.contains(attr)) continue;    #C
            token.attributes.put(attr,
claims.getStringClaim(attr));    #C
        }
        return Optional.of(token);
    } catch (ParseException | JOSEException e) {
        return Optional.empty();    #D
    }
}
```

#A Parse the encrypted JWT.
#B Decrypt and authenticate the JWT using the DirectDecrypter.
#C Extract any claims from the JWT.
#D Never reveal the cause of a decryption failure to the user.

You can now update the main method to switch to using the `EncryptedJwtTokenStore`, replacing the previous `EncryptedTokenStore`. You can reuse the AES key that you generated in section 6.3.2, but you'll need to cast it to the more specific `javax.crypto.SecretKey` class that the Nimbus library expects. Open Main.java and update the code to create the token controller again:

```
TokenStore tokenStore = new EncryptedJwtTokenStore(
    (SecretKey) encKey);    #A
var tokenController = new TokenController(tokenStore);
```

#A Cast the key to the more specific SecretKey class.

Restart the API and try it out: