You can use this basic functionality to construct a simple HTML browser for Natter messages, as shown in figure 9.4. The browser consists of a simple HTML page with a read-only capability URI contained in a link. When the link is clicked, the `getCap` function is called to load the messages in the space. The REST API call to retrieve the messages will return an array of read-only capability URIs for each message, which are then fetched in turn to populate the table. Listing 9.10 shows the HTML page. Create a new file named capability.html alongside the capability.js file you just created and copy the contents of the listing. Replace the link in the HTML with the `messages-r` link from a `createSpace` API call.

> **TIP** The capability URIs created with the `DatabaseTokenStore` don't work after a restart of the API server. You may find it easier to complete these exercises if you switch to a stateless token store such as the `JsonTokenStore` wrapped in the `HmacTokenStore`.




Figure 9.4 The simple HTML message browser. Clicking the "Load messages" link loads all messages into the table using read-only capability URIs.