nginx/user-guide/nginx-configuration/annotations/ for a list of features that can be enabled). Listing 10.20 shows the configuration for the Natter ingress controller. To allow Linkerd to automatically apply mTLS to connections between the ingress controller and the backend services, you need to rewrite the Host header from the external value (such as api.natter.local) to the internal name used by your service. This can be achieved by adding the `nginx.ingress.kubernetes.io/upstream-vhost` annotation. The NGINX configuration defines variables for the service name, port, and namespace based on the configuration so you can use these in the definition. Create a new file named natter-ingress.yaml in the kubernetes folder with the contents of the listing, but don't apply it just yet. There's one more step you need before you can enable TLS.

> TIP If you're not using a service mesh, your ingress controller may support establishing its own TLS connections to backend services or proxying TLS connections straight through to those services (known as *SSL passthrough*). Istio includes an alternative ingress controller, Istio Gateway, that knows how to connect to the service mesh.

Listing 10.20 Configuring ingress

```
apiVersion: extensions/v1beta1
kind: Ingress    #A
metadata:
  name: api-ingress    #B
  namespace: natter-api    #B
  annotations:
    nginx.ingress.kubernetes.io/upstream-vhost:    #C
```