updated when the secret changes, while environment variables can only be changed by restarting the pod.

Listing 11.11 shows how to expose the Natter database username and password to the pods in the Natter API deployment. A secret volume is defined in the `volumes` section of the pod spec, referencing the named secret to be exposed. In a `volumeMounts` section for the individual container you can then mount the secret volume on a specific path in the filesystem.

Listing 11.11 Exposing a secret to a pod

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: natter-api-deployment
  namespace: natter-api
spec:
  selector:
    matchLabels:
      app: natter-api
  replicas: 1
  template:
    metadata:
      labels:
        app: natter-api
    spec:
      securityContext:
        runAsNonRoot: true
      containers:
        - name: natter-api
          image: apisecurityinaction/natter-api:latest
          imagePullPolicy: Never
          volumeMounts:
            - name: db-password    #A
```