> **NOTE** The examples in this section assume you are familiar with UDP network programming in Java. See https://docs.oracle.com/javase/tutorial/networking/datagrams/index.html for an introduction.

To poll the engine, you call the `sslEngine.getHandshakeStatus()` method, which returns one of the following values, as shown in figure 12.3:

- `NEED_UNWRAP` indicates that the engine is waiting to receive a new message from the server. Your application code should call the `receive()` method on its UDP `DatagramChannel` to receive a packet from the server, and then call the `SSLEngine.unwrap()` method passing in the data it received.
- `NEED_UNWRAP_AGAIN` indicates that there is remaining input that still needs to be processed. You should immediately call the `unwrap()` method again with an empty input buffer to process the message. This can happen if multiple DTLS records arrived in a single UDP packet.
- `NEED_WRAP` indicates that the engine needs to send a message to the server. The application should call the `wrap()` method with an output buffer that will be filled with the new DTLS message, which your application should then send to the server.
- `NEED_TASK` indicates that the engine needs to perform some (potentially expensive) processing, such as performing cryptographic operations. You can call the `getDelegatedTask()` method on the engine to get one or more `Runnable` objects to execute. The method returns null when there are no more tasks to run. You can