```
            buffer.flip();
            var data = UTF_8.decode(buffer).toString();    #D
            logger.info("Received: {}", data);    #D
            buffer.compact();
        }
    }
}
```

#A Create the DtlsDatagramChannel and bind to port 54321
#B Allocate a buffer for data received from the client
#C Receive decrypted UDP packets from the client
#D Print out the received data

You can now start the server by running the following command:

```
mvn clean compile exec:java \
  -Dexec.mainClass=com.manning.apisecurityinaction.DtlsServer
```

This will produce many lines of output as it compiles and runs the code. You'll see the following line of output once the server has started up and is listening for UDP packets from clients:

```
[com.manning.apisecurityinaction.DtlsServer.main()] INFO
[CA]com.manning.apisecurityinaction.DtlsServer - Listening on
port
[CA]54321
```

You can now run the client in another terminal window by running