


Figure 13.2 When the device connects to the API it sends a PSK identifier in the TLS ClientKeyExchange message. The API can use this to find a matching device profile with an encrypted PSK for that device. The API decrypts the PSK and then completes the TLS handshake using the PSK to authenticate the device.

In this section, you'll adjust the `PskServer` from chapter 12 to look up the device profile during authentication. First, you need to load and initialize the device database. Open the PskServer.java file and add the following lines at the start of the `main()` method just after the PSK is loaded:

```
var psk = loadPsk(args[0].toCharArray());    #A
var encryptionKey = SecretBox.key();    #B
var deviceDb = Device.createDatabase(    #C
        SecretBox.encrypt(encryptionKey, psk));    #C
```

#A The existing line to load the example PSK
#B Create a new PSK encryption key
#C Initialize the database with the encrypted PSK