inside the server contains the `TlsContext` class, which has information about the connection. The PSK identity is stored inside the `SecurityParameters` class for the connection. Open the PskServer.java file and add the new method highlighted in bold in the listing. You can then retrieve the device identity after receiving a message by calling

```
var deviceId = server.getPeerDeviceIdentity();
```

> **CAUTION** You should only trust the PSK identity returned from `getSecurityParametersConnection()`, which are the final parameters after the handshake completes. The similarly named `getSecurityParametersHandshake()` contains parameters negotiated during the handshake process before authentication has finished and may be incorrect.

Listing 13.6 Exposing the device identity

```
var server = new PSKTlsServer(crypto,
        new DeviceIdentityManager(deviceDb, encryptionKey)) {
    @Override
    protected ProtocolVersion[] getSupportedVersions() {
        return ProtocolVersion.DTLSv12.only();
    }
    @Override
    protected int[] getSupportedCipherSuites() {
        return new int[] {
                CipherSuite.TLS_PSK_WITH_AES_128_CCM,
                CipherSuite.TLS_PSK_WITH_AES_128_CCM_8,
                CipherSuite.TLS_PSK_WITH_AES_256_CCM,
                CipherSuite.TLS_PSK_WITH_AES_256_CCM_8,
                CipherSuite.TLS_PSK_WITH_AES_128_GCM_SHA256,
```