```
                    break;
                case "authorization_pending":    #E
                    System.out.println("Still waiting!");
#E
                    break;
                default:
                    System.err.println("Authorization failed:
" + error);
                    System.exit(1);
                    break;
            }
        } else {
            System.out.println("Access token: " +     #F
                json.getString("access_token"));    #F
            break;
        }
    }
}
```

#A Start the authorization process and store the device code and poll interval
#B Display the verification URI and user code to the user
#C Poll the access token endpoint with the device code according to the poll interval
#D If the AS tells you to slow down then increase the poll interval by 5 seconds
#E Otherwise keep waiting until a response is received
#F The AS will return an access token when the authorization is complete

13.3.2 ACE-OAuth

The Authorization for Constrained Environments (ACE) working group at the IETF is working to adapt OAuth2 for IoT