account ID that you extracted earlier with the `aws sts get-caller-identity` command.

Enabling MFA for IAM users

We encourage you to enable MFA for all users. To enable MFA for your users, follow these steps:

1. Open the IAM service in the Management Console.
2. Choose Users at the left.
3. Click the myuser user.
4. Select the Security Credentials tab.
5. Click the Manage link near the Assigned MFA Device.
6. The wizard to enable MFA for the IAM user is the same one you used for enabling MFA for the AWS account root user.

We recommend enabling MFA for all users, especially for users granted administrator access to all or some services.

WARNING Stop using the AWS account root user from now on. Always use `myuser` and the new link to the Management Console.

WARNING You should never copy a user's access keys to an EC2 instance; use IAM roles instead! Don't store security credentials in your source code. And never ever check them into your source code repository. Try to use IAM roles instead whenever possible, as described in the next section.